

CONFIGURATION GUIDE FOR X-LITE SOFTPHONE

Step 1 Download Xlite soft phone here: <http://www.nomado.eu/support-download-configure-voip/softphone-sip-parameters-pc-mac-call>




Step 2 After creating your Nomado account, you will receive a system generated email for your SIP Parameter information. This contains your SIP Username (Internal Nomado Number) and SIP Password (6 digit, alphanumeric).


Step 3 You can see the 3 buttons at the upper center portion of the X-lite soft phone, the left button represents the <MENU> button, the center one is the <MINIMIZE> button, and the third one is the <HIDE> button. For SIP Account Settings, click on the <MENU> button and click on SIP Account Settings and click on Add.



Step 4 Enter the SIP Parameter Information. Take note: Display Name; User Name; and Authorization Name are the same, which is your SIP Username (Internal Nomado Number). On Domain, type sip.nomado.eu .Click on Domain button on the Domain Proxy.



Step 5 Click on the <TOPOLOGY> button. On STUN server, click the <Use specified server>. Then type stun01.sipphone.com:3478 then click on APPLY, then OK.




You will see that there's already account. simply click on the <CLOSE> button below. Then wait for a couple of seconds for your account to be registered.









ERROR CODES

1xx

2xx

3xx

4xx

5xx

6xx

Informational Responses

Successful Responses

Redirection Responses

Method Failures/Client Failure

Responses

Server Failures

Global Failures

SIP event

Cause

100 Trying

180 Ringing

181 Call Is Being Forwarded

182 Queued

183 Session Progress

extended search being performed may take a significant time so a forking proxy must send a 100 Trying response

200 OK

202 accepted

300 Multiple Choices

301 Moved Permanently

302 Moved Temporarily

305 Use Proxy

Success. This HTTP Status Code means everything is working fine. However, if you receive this message on screen, obviously something is not right... Please contact the server's administrator if this problem persists. Typically, this status code (as well as most other 200 Range codes) will only be written to your server logs.

Accepted. Request accepted but not completed yet, it will continue asynchronously.

The request is ambiguous and needs clarification as to which resource was requested

The resource has permanently moved elsewhere, the response indicates where it has gone to.

The resource has temporarily moved elsewhere, the response indicates where it is at present.

The request must be sent through the indicated proxy server.

380 Alternative Service	Operation failed because of invalid parameters and can not be retried (null parameter etc)
400 Bad request	Bearer capability not authorized. This error indicates that the credentials passed to the server do not match the credentials required to log on to the server. Please contact the Web server's administrator to verify that you have permission to access the requested resource.
401 Unauthorized	Call rejected
402 Payment required	Operation failed because of unauthorized access (invalid registrationId etc)
403 Forbidden	Unallocated (unassigned) number
404 Not found	Interworking, unspecified
405 Method not allowed	Interworking, unspecified
406 Not acceptable	Call rejected
407 Proxy authentication required	Recover on Expires timeout
408 Request timeout	Temporary failure
409 Conflict	Unallocated (unassigned) number
410 Gone	Interworking, unspecified
411 Length required	
412 Conditional Request Failed	
413 Request entity too long	Interworking, unspecified
414 Request URI (URL) too long	Interworking, unspecified
415 Unsupported media type	Operation failed because of not supported parameters (unsupported codecs)
416 Unsupported URI Scheme	
417 Unknown Resource-Priority	
420 Bad extension	Interworking, unspecified
421 Extension Required	
422 Session Interval Too Small	
423 Interval Too Brief	
428 Use Identity Header	
429 Provide Referrer Identity	
433 Anonymity Disallowed	
436 Bad Identity-Info	
437 Unsupported Certificate	
438 Invalid Identity Header	
480 Temporarily unavailable	No user response
481 Call leg does not exist	Interworking, unspecified
482 Loop detected	Interworking, unspecified
483 Too many hops	Interworking, unspecified
484 Address incomplete	Address incomplete (invalid number)



	format)
485 Address ambiguous	Unallocated (unassigned) number
486 Busy here	User busy
487 Request cancelled	Interworking, unspecified
488 Not acceptable here	Interworking, unspecified
489 Bad Event	
491 Request Pending	
493 Undecipherable (Could not decrypt S/MIME body part)	
494 Security Agreement Required	Temporary failure/Operation failed because of internal error in code (Null Pointer etc)
500 Internal server error	Service or option not implemented
501 Not implemented	Network out of order
502 Bad gateway	Service or option unavailable
503 Service unavailable	Recover on Expires timeout
504 Gateway timeout	Interworking, unspecified
505 Version not implemented	
513 Message Too Large	Resource unavailable, unspecified
580 Precondition Failed	User busy
600 Busy everywhere	Call rejected
603 Decline	Unallocated (unassigned) number
604 Does not exist anywhere	Bearer capability not presently available
606 Not acceptable	